



MM MM 000000 NN NN SSSSSSSS UU UU BBBB8888  
MM MM 000000 NN NN SSSSSSSS UU UU BBBB8888  
MMMM MMMM 00 00 NN NN SS SSSSSSSS UU UU BB 88  
MMMM MMMM 00 00 NN NN SS SSSSSSSS UU UU BB 88  
MM MM MM 00 00 NNNN NN SS SSSSSS UU UU BB 88  
MM MM MM 00 00 NNNN NN SS SSSSSS UU UU BB 88  
MM MM MM 00 00 NN NN SSSSSS SS UU UU BBBB8888  
MM MM MM 00 00 NN NN SSSSSS SS UU UU BBBB8888  
MM MM MM 00 00 NN NN SSSSSS SS UU UU BB 88  
MM MM MM 00 00 NN NN SSSSSS SS UU UU BB 88  
MM MM MM 00 00 NN NN SSSSSS SS UU UU BB 88  
MM MM MM 00 00 NN NN SSSSSSSS UUUUUUUUUU BBBB8888  
MM MM 000000 NN NN SSSSSSSS UUUUUUUUUU BBBB8888  
MM MM 000000 NN NN SSSSSSSS UUUUUUUUUU BBBB8888

LL LL 111111 SSSSSSSS  
LL LL 111111 SSSSSSSS  
LL LL 11 SS  
LL LL 11 SS  
LL LL 11 SS  
LL LL 11 SS  
LL LL 11 SSSSSS  
LL LL 11 SSSSSS  
LL LL 11 SS  
LL LL 11 SS  
LL LL 11 SS  
LL LL 11 SS  
LLLLLLLLLLLL 111111 SSSSSSSS  
LLLLLLLLLLLL 111111 SSSSSSSS

16-SEP-1984 02:20  
15-SEP-1984 22:47

VAX/VMS Command Definition Utility (V4-001)  
\_S255\$DUA28:[MONITOR.SRC]MONSUB.CLD;1 (1)

Page 1

Version: 'V04-000'

COPYRIGHT (c) 1978, 1980, 1982, 1984 BY  
DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.  
ALL RIGHTS RESERVED.

THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED  
ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE  
INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER  
COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY  
OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY  
TRANSFERRED.

THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE  
AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT  
CORPORATION.

DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS  
SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.

MODIFIED BY:

V03-005	PRS1011	Paul R. Senn	29-Feb-1984	14:00
	add /FLUSH_INTERVAL qualifier			
V03-004	TLC1052	Thomas L. Cafarella	17-Feb-1984	11:00
	Add /BY_NODE qualifier and change /INPUT to accept a list (in support of multi-file summary capability).			
V03-003	SPC0007	Stephen P. Carney	24-Jun-1983	16:00
	Add EXECUTE subcommand.			
V03-002	TLC1042	Thomas L. Cafarella	19-Jun-1983	15:00
	Add /ITEM qualifier for homogeneous classes.			
V03-001	TLC1031	Thomas L. Cafarella	25-Apr-1983	16:00
	Identify routine name for SET command.			

module

MONSUB

define

verb

MONITOR

routine MONITOR\_CMD

parameter P1,

label=CLASS\_NAME,

value (list)

qualifier BEGINNING,

nonnegatable,

value



16-SEP-1984 02:20  
15-SEP-1984 22:47

VAX/VMS Command Definition Utility (V4-001) Page 2  
\_S255\$DUA28:[MONTUR.SRC]MONSUB.CLD;1 (1)

```
57      qualifier ENDING,      nonnegatable,  
58      value  
59      qualifier INTERVAL,    nonnegatable,  
60      value  
61      qualifier FLUSH_INTERVAL, nonnegatable,  
62      value  
63      qualifier VIEWING_TIME, nonnegatable,  
64      value  
65      qualifier INPUT,      value (list)  
66      qualifier DISPLAY,    value, default  
67      qualifier RECORD,     value  
68      qualifier SUMMARY,    value  
69      qualifier COMMENT,    value  
70      qualifier BY_NODE  
71  
72      qualifier ALL,         nonnegatable, placement=local  
73      qualifier CURRENT,    nonnegatable, placement=local  
74      qualifier AVERAGE,   nonnegatable, placement=local  
75      qualifier MINIMUM,    nonnegatable, placement=local  
76      qualifier MAXIMUM,    nonnegatable, placement=local  
77  
78      qualifier TOPCPU,     nonnegatable, placement=local  
79      qualifier TOPDIO,     nonnegatable, placement=local  
80      qualifier TOPBIO,     nonnegatable, placement=local  
81      qualifier TOPFAULT,   nonnegatable, placement=local  
82  
83      qualifier CPU,        placement=local  
84  
85      qualifier PERCENT,    placement=local  
86  
87      qualifier ITEM,       nonnegatable, placement=local  
88      value (list)  
89  
90  define syntax      SET_DEFAULT_SYNTAX  
91      routine      SET_CMD  
92      parameter    P1,      label=DEFAULT_KEYWORD,  
93      value(required)  
94      parameter    P2,      label=CLASS_NAME,  
95      value (list)  
96      qualifier    BEGINNING, nonnegatable,  
97      value  
98      qualifier    ENDING,     nonnegatable,  
99      value  
100     qualifier    INTERVAL,   nonnegatable,  
101     value  
102     qualifier    FLUSH_INTERVAL, nonnegatable,  
103     value  
104     qualifier    VIEWING_TIME, nonnegatable,  
105     value  
106     qualifier    INPUT,      value (list)  
107     qualifier    DISPLAY,    value, default  
108     qualifier    RECORD,     value  
109     qualifier    SUMMARY,    value  
110     qualifier    COMMENT,    value  
111     qualifier    BY_NODE  
112
```

K 1  
16-SEP-1984 02:20  
15-SEP-1984 22:47

VAX/VMS Command Definition Utility (V4-001) Page 3  
\_S255\$DUA28:[MONITOR.SRC]MONSUB.CLD;1 (1)

```
113     qualifier ALL,           nonnegatable, placement=local
114     qualifier CURRENT,       nonnegatable, placement=local
115     qualifier AVERAGE,       nonnegatable, placement=local
116     qualifier MINIMUM,       nonnegatable, placement=local
117     qualifier MAXIMUM,       nonnegatable, placement=local
118
119     qualifier TOPCPU,         nonnegatable, placement=local
120     qualifier TOPDIO,         nonnegatable, placement=local
121     qualifier TOPPIO,         nonnegatable, placement=local
122     qualifier TOPFAULT,      nonnegatable, placement=local
123
124     qualifier CPU,           placement=local
125
126     qualifier PERCENT,       placement=local
127
128     qualifier ITEM,          nonnegatable, placement=local
129                               value (list)
130
131 define type      SET_OPTIONS
132     keyword      DEFAULT,    syntax=SET_DEFAULT_SYNTAX
133
134 define type      SHOW_OPTIONS
135     keyword      DEFAULT
136
137 define verb      SET
138     routine      SET_CMD
139     parameter    P1,         label=SET_PARAMETER,
140                               value(required,type=SET_OPTIONS)
141
142 define           verb      INITIALIZE
143     routine      INIT_CMD
144
145 define           verb      SHOW
146     routine      SHODEF_CMD
147     parameter    P1,         label=SHOW_PARAMETER,
148                               value(default=DEFAULT,type=SHOW_OPTIONS)
149
150 define           verb      HELP
151     routine      HELP_CMD
152     parameter    P1,         label=HELP_KEYS,
153                               value(type=$REST_OF_LINE)
154
155 define           verb      EXIT
156     routine      EXIT_CMD
157
158 define           verb      EXECUTE
159     routine      EXECUTE_CMD
160     parameter    P1,         label=EXEC_FILE,
161                               value(default=MONITOR.MON)
```

\$ SET COMMAND/OBJ\$=OBJ\$:/LIS=LIS\$: SRC\$:MONSUB



0242 AH-BT13A-SE  
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION  
CONFIDENTIAL AND PROPRIETARY

MONMSG  
LIS

REQUEST  
LIS

SHODEF  
LIS

MONSUB  
LIS

PREPOST  
LIS

SUMMBUFF  
LIS